

Overview of all namoptions in DALES

Thijs Heus
Chiel van Heerwaarden
Johan van der Dussen
Huug Ouwersloot

August 21, 2015

Contents

Contents	III
1 Introduction	1
2 Namoptions overview	3
2.1 Main modules	3
2.1.1 Namelist DOMAIN	3
2.1.2 Namelist DYNAMICS	4
2.1.3 Namelist PHYSICS	5
2.1.4 Namelist RUN	8
2.1.5 Namelist NAMSUBGRID	9
2.2 Extra modules	10
2.2.1 Namelist NAMAGScross	10
2.2.2 Namelist NAMBUDGET	10
2.2.3 Namelist NAMBULKMICROSTAT	10
2.2.4 Namelist NAMCANOPY	10
2.2.5 Namelist NAMCAPE	11
2.2.6 Namelist NAMCHECKSIM	12
2.2.7 Namelist NAMCHEM	12
2.2.8 Namelist NAMCLOUDFIELD	13
2.2.9 Namelist NAMCROSSSECTION	13
2.2.10 Namelist NAMDE	13
2.2.11 Namelist NAMFIELD_DUMP	14
2.2.12 Namelist NAMGENSTAT	14
2.2.13 Namelist NAMHETEROSTATS	14
2.2.14 Namelist NAMLSMCROSSSECTION	15
2.2.15 Namelist NAMLSMSTAT	15
2.2.16 Namelist NAMMICROPHYSICS	15
2.2.17 Namelist NAMNETCDFSTATS	16
2.2.18 Namelist NAMNUUDGE	16
2.2.19 Namelist NAMPARTICLES	17
2.2.20 Namelist NAMprojection	17
2.2.21 Namelist NAMquadrant	17
2.2.22 Namelist NAMRADIATION	18
2.2.23 Namelist NAMRADSTAT	20
2.2.24 Namelist NAMSAMPLING	20
2.2.25 Namelist NAMSIMPLEICESTAT	21
2.2.26 Namelist NAMSTATTEND	21

CONTENTS

2.2.27 Namelist NAMSTRESS	22
2.2.28 Namelist NAMSURFACE	22
2.2.29 Namelist NAMTILT	24
2.2.30 Namelist NAMTIMESTAT	24
Bibliography	27

Chapter 1

Introduction

This document gives an overview of all namelist options in version 4.1 of the Dutch Atmospheric Large Eddy Simulation (DALES) model. Only general information concerning these options is presented. For more detailed information about the model, the reader is referred to Heus et al. (2009).

Chapter 2

Namoptions overview

All options that can be set for the LES experiments will be discussed in the following paragraphs. These options are listed in a separate paragraph for all name lists. For all name lists, the options are given with their default values, possible values, a description and the unit. The possible values are denoted by an x . The paragraphs are grouped in two sections. In the first section, the main modules are discussed. In the second section an overview of the extra modules is presented.

2.1 Main modules

2.1.1 Namelist DOMAIN

Option	Default	Possible values	Description	Unit
itot	64	$x = n \cdot \text{nprocx}$, $n \in \mathbb{N}^*$	Number of horizontal grid points in x-direction	-
jtot	64	$x = n \cdot \text{nprocy}$, $n \in \mathbb{N}^*$	Number of horizontal grid points in y-direction	-
kmax	96	$x \in \mathbb{N}^*$	Number of vertical grid points	-
xsize	-1	$x \in \mathbb{N}^*$	Horizontal size of the simulated domain	m
ysize	-1	$x \in \mathbb{N}^*$	Horizontal size of the simulated domain	m
xlat	52	$x \in \mathbb{R}$, $-90 \leq x \leq 90$	Latitude	°
xlon	0	$x \in \mathbb{R}$, $0 \leq x \leq 360$	Longitude	°
xday	1	$x \in \mathbb{R}$, $1 \leq x \leq 365$	Number of the day	-
xtime	0	$x \in \mathbb{R}$, $0 \leq x < 24$	UTC time of the day	h
ksp	$\min(\frac{3}{4}\text{kmax}, \text{kmax} - 15)$	$x \in \mathbb{N}^*$	Lower height of sponge layer	-

2.1.2 Namelist DYNAMICS

Option	Default	Possible values	Description	Unit
cu	0	$x \in \mathbb{R}$	Transformation velocity of the Galilei transformation in x-direction	m s^{-1}
cv	0	$x \in \mathbb{R}$	Transformation velocity of the Galilei transformation in y-direction	m s^{-1}
llsadv	.false.	$x \in \{\text{.false., .true.}\}$	Switch for large scale forcings	-
lqlnr	.true.	$x \in \{\text{.false., .true.}\}$	Switch for Newton-Raphson approximation of the liquid water content	-
lnoclouds	.false.	$x \in \{\text{.false., .true.}\}$	Switch to disable θ_l calculations	-
iadv_mom iadv_tke iadv_thl iadv_qt iadv_sv(1:nsv)	{ 5 -1 -1 -1 -1 }	$x \in \{1, 2, 5, 52, 55, 6, 62, 7\}$	Advection scheme for momentum, TKE, θ_l , q_t and scalars: 1 = 1 st order upwind 2 = 2 nd order central difference 5 = Option 6 + 5 th order upwind 52 = Horizontal 5 th & vertical 2 nd 55 = Hybrid scheme 6 = 6 th order central difference 62 = Horizontal 6 th & vertical 2 nd 7 = Kappa scheme	-
ibas_prf	3	$x \in \{1, 2, 3, 4, 5\}$	Flag for density calculations based on 1 = Constant θ_v 2 = Boussinesq-like (similar to DALES 3) 3 = Standard lapse rate, based on surface temp. 4 = Standard lapse rate, based on $T_{surf} = 15^\circ\text{C}$ 5 = User defined (using the file baseprof.inp.###)	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
lambda_crit	100	$x \in \mathbb{R}$	Maximum value for the smoothness. This controls if WENO for the hybrid advection scheme	-

2.1.3 Namelist PHYSICS

Option	Default	Possible values	Description	Unit
thls	-1	$x \in \mathbb{R}, x > 0$	Liquid water potential temperature at the surface	K
ps	-1	$x \in \mathbb{R}, x > 0$	Pressure at the surface	Pa
isurf	-1	$x \in \{1, 2, 3, 4, 10\}$	Flag for surface parametrization 1 = Interactive scheme (using radiation) 2 = Forced surface temperature; fluxes are calculated 3 = Forced momentum, moisture and heat flux; surface temperature is calculated 4 = Forced moisture and heat flux; u_* and surface temperature are calculated 10 = User defined surface scheme. Can only be used for certain cases (using the file moduser.f90)	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
z0	-1	$x \in \mathbb{R}, x > 0$	Surface roughness	m
ustin	-1	$x \in \mathbb{R}, x > 0$	Prescribed friction velocity	m s^{-1}
wtsurf	-1	$x \in \mathbb{R}, x > 0$	Flux of liq. water pot. temp. at the surface	K m s^{-1}
wqsurf	-1	$x \in \mathbb{R}$	Flux of total water content	kg kg^{-1}
wsvsurf(1:nsv)	0	$x \in \mathbb{R}$	Flux of scalar n at the surface	m s^{-1}
ltimedep	.false.	$x \in \{\text{.false., .true.}\}$	Switch for timedependent fluxes and large scale forcings	-
lcoriol	.true.	$x \in \{\text{.false., .true.}\}$	Switch for coriolis force	-
igrw_damp	2	$x \in \{-1, 0, 1, 2, 3\}$	Flag for gravity wave damping 0 = no damping 1 = fast damping of wind to average wind & slow damping of average to geowind 2 = fast damping of wind to geowind 3 = fast damping of wind to average wind -1 = nudging grid averaged wind to wind field provided by lscale.inp	-
geodamptime	7200	$x \in \mathbb{R}, x > 0$	Time scale for nudging to geowind in sponge layer	s
lmomsubs	.false.	$x \in \{\text{.false., .true.}\}$	Switch to apply subsidence on momentum	-
lmoist	.true.	$x \in \{\text{.false., .true.}\}$	Switch for calculation of moisture fields	-
chi_half	0.5	$x \in \mathbb{R}, 0 \leq x \leq 1$	Wet, dry or intermediate (default) mixing over the cloud edge	-
timerad	0	$x \in \mathbb{R}, x > 0$	Value for sampling interval of radiation scheme	s
iradiation	0	$x \in \{0, 1, 2, 3, 4, 10\}$	Flag for radiation calculations 0 = No radiation 1 = Full radiation 2 = Parametrized radiation 3 = Simple surface radiation for land surface model 4 = Radiation using the rapid radiative transfer model 10 = User defined radiation (use rad_user.f90)	-

Continued from previous page

Option	Default	Possible values	Description	Unit
useMcICA	.true.	$x \in \{\text{.false., .true.}\}$	Switch for the Monte Carlo Independent Column Approach	-
rad_ls	.true.	$x \in \{\text{.false., .true.}\}$	Switch for prescribed radiative forcing	-
rad_longw	.true.	$x \in \{\text{.false., .true.}\}$	Switch for parametrized longwave radiative forcing	-
rad_shortw	.true.	$x \in \{\text{.false., .true.}\}$	Switch for parametrized shortwave radiative forcing	-
rad_smoke	.false.	$x \in \{\text{.false., .true.}\}$	Switch for longwave divergence for smoke cloud	-
irad	-1	$x \in \{-1, 0, 1, 2, 3, 4, 10\}$	Deprecated flag to force (irradiation, rad_ls, rad_longw, rad_shortw, rad_smoke) -1 = - 0 = (0,-,-,-) 1 = (2,.true.,.false.,.false.,.false.) 2 = (2,.false.,.true.,.false.,.false.) 3 = (1,-,-,-) 4 = (2,.false.,.true.,.true.,.false.) 10 = (2,.false.,.false.,.false.,.true.)	-
rka	130	$x \in \mathbb{R}, x > 0$	Extinction coefficient (used if irradiation = 2)	$\text{m}^2 \text{ kg}^{-1}$
dlwbot	0	$x \in \mathbb{R}, x \geq 0$	Longwave radiative flux jump at cloud bottom	W m^{-2}
dlwtop	74	$x \in \mathbb{R}, x \geq 0$	Longwave radiative flux jump at cloud top	W m^{-2}
sw0	1100	$x \in \mathbb{R}, x \geq 0$	Direct solar radiative component cloud top (assumes zero diffusive contribution)	W m^{-2}
gc	0.85	$x \in \mathbb{R}, 0 \leq x \leq 1$	Asymmetry factor of droplet scattering angle distribution; overwritten to 0.64 if laero = .true.	-
reff	1e-5	$x \in \mathbb{R}, x > 0$	Cloud drop effective radius	m
isvsmoke	1	$x \in \mathbb{N}^*, x \leq \text{nsv}$	Scalar field to be used for optical depth calculation (when rad_smoke = .true.)	-
lforce_user	.false.	$x \in \{\text{.false., .true.}\}$	Switch for user-defined forcing. Can only be used for certain cases (using the file moduser.f90)	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
lcloudshading	.false.	$x \in \{\text{.false., .true.}\}$	Switch to let clouds shade the surface for rad_lsm	-
lrigidlid	.false.	$x \in \{\text{.false., .true.}\}$	Switch to enable simulations with a rigid lid	-
unudge	1	$x \in \mathbb{R}, \quad 0 \leq x \leq 1$	Nudging factor if igrw_damp is -1	-

2.1.4 Namelist RUN

Option	Default	Possible values	Description	Unit
iexpnr	0	$x \in \mathbb{N}, \quad 0 \leq x < 1000$	Experiment number; every output filename ends with [.iexpnr]	-
dtmax	20	$x \in \mathbb{R}, \quad x > 0$	Maximum timestep that is used by the model	s
runtime	300	$x \in \mathbb{R}, \quad x > 0$	Total simulation (or: run) time	s
lwarmstart	.false.	$x \in \{\text{.false., .true.}\}$	Flag for a “cold” or a “warm” start	-
startfile	-	$x = \text{initd}##\text{h}##\text{m}xxx.\#\#$	Basis for the name of the restartfiles	-
trestart	3600	$x \in \mathbb{R}, \quad x > 0$	Each <i>trestart</i> seconds, a restart file is written to disk	s
dtav_glob	60	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Global value for sampling interval of statistical routines	s
timeav_glob	3600	$x = n \cdot dtav_glob, \quad n \in \mathbb{N}^*$	Global value for writing interval of statistical routines	s
irandom	0	$x \in \mathbb{Z}$	Number to feed randomizer with	-
krand	kmax	$x \in \mathbb{N}, \quad 1 \leq x \leq kmax$	Top vertical full level of randomization	-
randqt	1e-5	$x \in \mathbb{R}, \quad x \geq 0$	Amplitude of randomization of qt	kg kg^{-1}
randthl	0.1	$x \in \mathbb{R}, \quad x \geq 0$	Amplitude of randomization of thl	K
nsv	0	$x \in \mathbb{N}, \quad 0 \leq x \leq 100$	Number of additional passive scalars	-
ladaptive	.false.	$x \in \{\text{.false., .true.}\}$	If .true., this allows the model to vary time step, depending on numerical stability criteria	-
courant	0.7 or 1*	$x \in \mathbb{R}, \quad x > 0$	Courant number	-
peclet	0.15	$x \in \mathbb{R}, \quad x > 0$	Peclet number	-
author	“”	$x = \text{“....”}$	Name of the author	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
krandumin	1	$x \in \mathbb{N}^*, x \leq kmax$	Bottom vertical full level of wind randomization	-
krandumax	0	$x \in \mathbb{N}, x \leq kmax$	Top vertical full level of wind randomization	-
randu	0.5	$x \in \mathbb{R}, x \geq 0$	Amplitude of randomization of wind speed	m s^{-1}
nprocx	1	$x = N_{\text{processors}}/n, n, x \in \mathbb{N}^*$	Number of processors in x direction; if set to 0, MPI will determine suitable value	-
nprocy	0	$x = N_{\text{processors}}/\text{nprocx}$	Number of processors in y direction; if set to 0, MPI will determine suitable value	-

*If iadv_mom $\in \{6, 62\}$ or any value of iadv_tke, iadv_thl, iadv_qt or iadv_sv $\in \{6, 62, 7\}$, courant = 0.7 as standard. Otherwise default value is 1.

2.1.5 Namelist NAMSUBGRID

Option	Default	Possible values	Description	Unit
ldelta	.false.	$x \in \{\text{.false., .true.}\}$	Switch for diminished sfs in stable flow	-
lmason	.false.	$x \in \{\text{.false., .true.}\}$	Switch for decreased length scale near the surface	-
cf	2.5	$x \in \mathbb{R}, x > 0$	Filter constant	-
cn	0.76	$x \in \mathbb{R}, x > 0$	Subfilter scale parameter	-
Rigc	0.25	$x \in \mathbb{R}, x > 0$	Critical Richardson number	-
Prandtl	$\frac{1}{3}$	$x \in \mathbb{R}, x > 0$	Prandtl number	-
lsmagorinsky	.false.	$x \in \{\text{.false., .true.}\}$	Switch for smagorinsky subgrid scheme	-
cs	-1	$x \in \mathbb{R}, x > 0$	Smagorinsky constant	-
nmason	2	$x \in \mathbb{R}, x > 0$	Exponent in Mason correction function	-
sgs_surface_fix	.false.	$x \in \{\text{.false., .true.}\}$	Switch to apply a fix to the coupling of SFS TKE to the surface (experimental)	-

2.2 Extra modules

2.2.1 Namelist NAMAGScross

Option	Default	Possible values	Description	Unit
lAGScross	.false.	$x \in \{\text{.false., .true.}\}$	Switch to enable A-g _s specific output; requires lrsags = .true.	-
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s

2.2.2 Namelist NAMBUDGET

Option	Default	Possible values	Description	Unit
lbudget	.false.	$x \in \{\text{.false., .true.}\}$	Switch for turbulent TKE budget calculation	-
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot dtav, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.3 Namelist NAMBULKMICROSTAT

Option	Default	Possible values	Description	Unit
lmicrostat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for microphysics statistics calculation	-
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot dtav, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.4 Namelist NAMCANOPY

Option	Default	Possible values	Description	Unit
lcanopy ncanopy	.false. 10	$x \in \{\text{.false., .true.}\}$ $x \in \mathbb{N}^*, x \leq kmax$	Switch to represent canopy drag Amount of layers that contain canopy	- -

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
cd	0.15	$x \in \mathbb{R}, x > 0$	Drag coefficient	-
lai	2	$x \in \mathbb{R}, x \geq 0$	One-sided plant area index of the canopy	-
lpaddistr	.false.	$x \in \{\text{.false., .true.}\}$	Switch to make use of customized plant area density (prescribed at half levels in paddistr.inp)	-
npaddistr	11	$x \in \mathbb{N}, x \geq 2$	Amount of half levels prescribed in paddistr.inp	-
wth_can	0	$x \in \mathbb{R}$	Prescribed SH canopy flux (at top)	K m s^{-1}
wqt_can	0	$x \in \mathbb{R}$	Prescribed LE canopy flux (at top)	$\text{kg kg}^{-1} \text{m s}^{-1}$
wsv_can(1:100)	0	$x \in \mathbb{R}$	Prescribed scalar flux (at top)	ppb m s^{-1}
wth_total	.false.	$x \in \{\text{.false., .true.}\}$	If true, wth_can is including the surface flux	-
wqt_total	.false.	$x \in \{\text{.false., .true.}\}$	If true, wqt_can is including the surface flux	-
wsv_total(1:100)	.false.	$x \in \{\text{.false., .true.}\}$	If true, wth_sv is including the surface flux	-
wth_alpha	0	$x \in \mathbb{R}$	Decay constant for SH with integrated PAD	-
wqt_alpha	0	$x \in \mathbb{R}$	Decay constant for LE with integrated PAD	-
wsv_alpha(1:100)	0	$x \in \mathbb{R}$	Decay constant for scalar fluxes with integrated PAD	-

2.2.5 Namelist NAMCAPE

Option	Default	Possible values	Description	Unit
lcape	.false.	$x \in \{\text{.false., .true.}\}$	Switch to turn CAPE crosssections on and off	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, n \in \mathbb{N}^*$	Time interval for sampling of statistics	s

2.2.6 Namelist NAMCHECKSIM

Option	Default	Possible values	Description	Unit
tcheck	0	$x \in \mathbb{R}, x \geq 0$	Time interval between checks of velocity divergence and Courant numbers	s

2.2.7 Namelist NAMCHEM

Option	Default	Possible values	Description	Unit
lchem	.false.	$x \in \{\text{.false., .true.}\}$	Switch to turn chemistry on and off	-
tnor	-	$x \in \mathbb{N}, x \geq N_{\text{reactions}}$	Number of chemical reactions	-
firstchem	1	$x \in \mathbb{N}, 1 \leq x \leq \text{lastchem}$	Column number in scalar.inp of first chemical	-
lastchem	nsv	$x \in \mathbb{N}, \text{firstchem} \leq x \leq \text{nsv}$	Column number in scalar.inp of last chemical	-
ldiuvar	.false.	$x \in \{\text{.false., .true.}\}$	Switches diurnal photolysis reaction rates	-
h_ref	12	$x \in \mathbb{R}, 0 \leq x < 24$	Hour used to calculate photolysis rates if ldiuvar = .false.	h
lcloudKconst	.false.	$x \in \{\text{.false., .true.}\}$	Switch to make photolysis reaction rates independent of cloud presence if .true.	-
lchconst	.false.	$x \in \{\text{.false., .true.}\}$	Reaction rates are based on t_ref p_ref and q_ref instead of calculated T, p and q if .true.	-
t_ref	298	$x \in \mathbb{R}, x \geq 0$	Reference temperature	K
q_ref	5.e-3	$x \in \mathbb{R}, x \geq 0$	Reference humidity	kg kg^{-1}
p_ref	100000	$x \in \mathbb{R}, x > 0$	Reference pressure	Pa
lchmovie	.false.	$x \in \{\text{.false., .true.}\}$	Switch for extra output to make movies	-
dtchmovie	60	$x \in \mathbb{R}, x > 0$	Time interval to write extra output	s
lsegr	.false.	$x \in \{\text{.false., .true.}\}$	Switch for information about segregation in a Mixed Layer approach	-

2.2.8 Namelist NAMCLOUDFIELD

Option	Default	Possible values	Description	Unit
lcloudfield	.false.	$x \in \{\text{.false., .true.}\}$	Switch for cloud field calculations	-
laddinfo	.false.	$x \in \{\text{.false., .true.}\}$	Switch to enable writing of q_l and w values	-
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s

2.2.9 Namelist NAMCROSSESECTION

Option	Default	Possible values	Description	Unit
lcross	.false.	$x \in \{\text{.false., .true.}\}$	Switch for dumping of crosssections of the field	-
lbinary	.false.	$x \in \{\text{.false., .true.}\}$	Switch to dump crosssections in binary files	-
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
crossheight(1:100)	1: $x = 2$	$x \in \mathbb{N}, \quad 1 \leq x \leq kmax$	Heights of the horizontal crosssection	-
crossplane	2	$x \in \mathbb{N}, \quad 1 \leq x \leq jtot/N_{processors}$	Location of the vertical (xz) plane on every processor	-
crossortho	2	$x \in \mathbb{N}, \quad 1 \leq x \leq itot$	Location of the vertical (yz) plane	-

2.2.10 Namelist NAMDE

Option	Default	Possible values	Description	Unit
SSA	0.999	$x \in \mathbb{R}, \quad 0 \leq x \leq 1$	Representative single scattering albedo	-
laero	.false.	$x \in \{\text{.false., .true.}\}$	Switch to use aerosols instead of clouds for Delta-Eddington calculations	-
iDE	1	$x \in \mathbb{N}^*, x \leq nsv$	Scalar field used as aerosols if laero set to .true.	-

2.2.11 Namelist NAMFIELDDDUMP

Option	Default	Possible values	Description	Unit
lfielddump	.false.	$x \in \{\text{.false., .true.}\}$	Switch for dumping of 3d-fields	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
lbinary	.false.	$x \in \{\text{.false., .true.}\}$	Switch to dump crosssections in binary files	-
ldiracc	.false.	$x \in \{\text{.false., .true.}\}$	Switch to dump into binary direct access files instead of Fortran unformated files	-
klow	1	$x \in \mathbb{N}, \quad 1 \leq x \leq \text{khigh}$	Lowest level of the 3d-field output	-
khight	k_{\max}	$x \in \mathbb{N}, \quad \text{klow} \leq x \leq k_{\max}$	Highest level of the 3d-field output	-

2.2.12 Namelist NAMGENSTAT

Option	Default	Possible values	Description	Unit
lstat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculating generic slabaveraged statistics	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.13 Namelist NAMHETEROSTATS

Option	Default	Possible values	Description	Unit
lheterostats	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculating generic x -averaged statistics	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
ncklimit	k_{\max}	$x \in \mathbb{N}^*, \quad x \leq k_{\max}$	Maximum height index for which x -averages are calculated and written	-

2.2.14 Namelist NAMLSMCROSSSECTION

Option	Default	Possible values	Description	Unit
lcross	.false.	$x \in \{\text{.false., .true.}\}$	Switch to activate dumping of projections in the land surface layer	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
crossheight	2	$x \in \mathbb{N}^*, \quad x \leq 4$	Height of the xy-projection	-
crossplane	2	$x \in \mathbb{N}^*, \quad x \leq \frac{j_{\text{tot}}}{n_{\text{procy}}}$	Position of the xz-plane on every processor	-

2.2.15 Namelist NAMLSMSTAT

Option	Default	Possible values	Description	Unit
lstat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculating land surface statistics	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.16 Namelist NAMMICROPHYSICS

Option	Default	Possible values	Description	Unit
imicro	0	$x \in \{0, 1, 2, 3, 5, 10\}$	Flag for the microphysical scheme: 0 = No microphysics (all-or-nothing scheme) 1 = Drizzle microphysics 2 = Bulk microphysics 3 = Bin microphysics (inactive) 5 = Simple ice microphysics 10 = User defined microphysics. Can only be used for certain cases (using the file moduser.f90)	-
l_sb	.true.	$x \in \{\text{.false., .true.}\}$	Switch for KK00 (Khairotdinov and Kogan, 2000) or SB (Seifert and Beheng, 2001, 2006) scheme resp.	-

Continued from previous page

Option	Default	Possible values	Description	Unit
l_sedc	.true.	$x \in \{\text{.false., .true.}\}$	Switch for cloud droplet sedimentation	-
l_rain	.true.	$x \in \{\text{.false., .true.}\}$	Switch for rain formation and evolution	-
l_mur_cst	.false.	$x \in \{\text{.false., .true.}\}$	Switch for a constant value of μ_r (in raindrop gamma distribution)	-
l_berry	.true.	$x \in \{\text{.false., .true.}\}$	Berry-Hsie autoconversion instead of Kessler-Lin	-
l_graupel	.true.	$x \in \{\text{.false., .true.}\}$	Switch for graupel	-
l_warm	.false.	$x \in \{\text{.false., .true.}\}$	Check: rune ice micro in warm mode	-
mur_cst	5	$x \in \mathbb{R}, \quad x > 0$	Value for μ_r , a shape parameter for the rain drop number density distribution (used only if l_mur_cst = .true.)	-
Nc_0	70e6	$x \in \mathbb{R}, \quad x \geq 0$	Initial number of cloud droplets	-
sig_g	1.34	$x \in \mathbb{R}, \quad x \geq 0$	Geometric standard deviation of the cloud droplet drop size distribution	-
sig_gr	1.5	$x \in \mathbb{R}, \quad x \geq 0$	Geometric standard deviation of the rain droplet drop size distribution	-

2.2.17 Namelist NAMNETCDFSTATS

Option	Default	Possible values	Description	Unit
lncdf	.true.	$x \in \{\text{.false., .true.}\}$	Switch to write NetCDF output	-

2.2.18 Namelist NAMNUUDGE

Option	Default	Possible values	Description	Unit
lnudge	.false.	$x \in \{\text{.false., .true.}\}$	Switch to activate/deactivate nudging	-
tnudgefac	1	$x \in \mathbb{R}, \quad x > 0$	Nudgefactor	-

2.2.19 Namelist NAMPARTICLES

Option	Default	Possible values	Description	Unit
lpartic	.false.	$x \in \{\text{.false., .true.}\}$	Switch to enable/disable this routine	-
lpartsgs	.true.	$x \in \{\text{.false., .true.}\}$	Switch for subgrid diffusion	-
intmeth	3	$x \in \{0, 3\}$	Flag for time integration scheme 0 = particles stand still 3 = Adams-Bashforth second order scheme	-
lstat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for particle statistics	-
dtav	60	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	3600	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s
ldump	.false.	$x \in \{\text{.false., .true.}\}$	Switch for dump of particle field	-
timedump	3600	$x \in \mathbb{R}, \quad x > 0$	Time interval for particle field dump	s
npartdump	10	$x \in \mathbb{N}, \quad 0 \leq x \leq 10$	Number of variables written at <i>timedump</i> , in order: $x, y, z, u, v, w, \theta_l, \theta_v, q_t, q_l$	-

2.2.20 Namelist NAMprojection

Old version of modcrosssection (Paragraph 2.2.9). Usage of modprojection is not advised.

Option	Default	Possible values	Description	Unit
lproject	.false.	$x \in \{\text{.false., .true.}\}$	Switch to activate dumping of projections of the field	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
projectheight	2	$x \in \mathbb{N}^*, \quad x \leq \text{kmax}$	Height of the xy-projection	-

2.2.21 Namelist NAMquadrant

Option	Default	Possible values	Description	Unit
lquadrant	.false.	$x \in \{\text{.false., .true.}\}$	Switch to enable quadrant-hole analysis	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
dtav	dtav_glob	$x = n \cdot dtmax, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeavev hole	dtav 0	$x = n \cdot dtav, \quad n \in \mathbb{N}^*$ $x \in \mathbb{R}, \quad x \geq 0$	Time interval for writing statistics Hole size of Q-H analysis	s -
iwind	1	$x \in \{1, 2, 3\}$	Flag for which wind speed determines quadrant: 1: u 2: v 3: $\sqrt{u^2 + v^2}$	-
klow	2	$x \in \mathbb{N}, \quad 2 \leq x \leq khigh$	Lowest (half) level evaluated in Q-H analysis	-
khight	kmax	$x \in \mathbb{N}, \quad x \leq kmax$	Highest (half) level evaluated in Q-H analysis	-

2.2.22 Namelist NAMRADIATION

This namelist is only used if the Rapid Radiative Transfer Model for GCMs (RRTMG) is applied, i.e. irradiation = 4.

Option	Default	Possible values	Description	Unit
lCnstZenith	.false.	$x \in \{\text{.false., .true.}\}$	Switch to apply a fixed solar zenith angle	-
cnstZenith	0	$x \in \mathbb{R}, \quad x \leq 90$	Solar zenith angle if lCnstZenith = .true.	°
lCnstAlbedo	.false.	$x \in \{\text{.false., .true.}\}$	Switch to apply the constant albedoav as albedo instead of the parameterization in RRTMG	-
ioverlap	2	$x \in \{0, 1, 2, 3\}$	Flag for cloud overlap method: 0: Clear only 1: Random 2: Maximum/random 3: Maximum	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
inflglw	2	$x \in \{0, 1, 2\}$	Flag for RRTMG input: 0: Cloud fraction & optical depth 1: Cloud fraction & liquid water path 2: Cloud fraction & liquid water path & ice fraction	-
iceflglw	3	$x \in \{0, 1, 2, 3\}$	Flag for ice particle specification: Detailed information under "ice-flag" in rrtmg_lw_cldprop.f90	-
liqflglw	1	$x \in \{0, 1\}$	Flag for effect of liquid water: 0: optical depth computed as in CCM3 1: optical depth due to water clouds computed using water droplet effective radius input	-
inflgsw	2	$x \in \{0, 1, 2\}$	Flag for RRTMG input: 0: Cloud fraction & optical depth 1: Cloud fraction & liquid water path 2: Cloud fraction & liquid water path & ice fraction	-
iceflgsw	3	$x \in \{1, 2, 3\}$	Flag for ice particle specification: Detailed information under "ice-flag" in rrtmg_lw_cldprop.f90	-
liqflgsw	1	$x \in \{0, 1\}$	Flag for effect of liquid water: 0: optical depth computed as in CCM3 1: optical depth due to water clouds computed using water droplet effective radius input	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
ocean	.false.	$x \in \{\text{.false., .true.}\}$	Switch to calculate radiation over ocean	-
usero3	.false.	$x \in \{\text{.false., .true.}\}$	Switch to take O ₃ profile from backrad.inp instead of standard profile	-
co2factor	1	$x \in \mathbb{R}, \quad x \geq 0$	Multiplication factor for reading CO ₂ input by RRTMG	-
doperpetual	.false.	$x \in \{\text{.false., .true.}\}$	Switch to not use a diurnal cycle	-
doseasons	.true.	$x \in \{\text{.false., .true.}\}$	Switch to account for changes in Earth's position from day to day	-
iyear	1992	$x \in \mathbb{Z}$	Year of the simulation	-

2.2.23 Namelist NAMRADSTAT

Option	Default	Possible values	Description	Unit
lstat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculating slabaveraged radiation statistics	-
lradclearair	.false.	$x \in \{\text{.false., .true.}\}$	Another switch for calculating slabaveraged radiation statistics	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.24 Namelist NAMSAMPLING

Option	Default	Possible values	Description	Unit
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s
lsampcl	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling cloud ($q_l > 0$)	-
lsampco	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling cloud core ($q_l > 0, \theta'_v > 0$)	-
lsampup	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling updrafts ($w > 0$)	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
lsampbuup	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling of buoyant updrafts ($w > 0, \theta'_v > 0$)	-
lsampcldup	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling cloudy updrafts ($q_l > 0, w > 0$)	-
lsamptend	.false.	$x \in \{\text{.false., .true.}\}$	Switch for conditional sampling of tendencies	-

2.2.25 Namelist NAMSIMPLEICESTAT

Option	Default	Possible values	Description	Unit
lmicrostat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for simple ice microphysics statistics calculation	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.26 Namelist NAMSTATTEND

Option	Default	Possible values	Description	Unit
ltend	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculation of tendencies of prognostic variables	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.27 Namelist NAMSTRESS

Option	Default	Possible values	Description	Unit
lstress	.false.	$x \in \{\text{.false., .true.}\}$	Switch for turbulent stress budget	-
dtav	dtav_glob	$x = n \cdot \text{dtmax}, \quad n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot \text{dtav}, \quad n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.28 Namelist NAMSURFACE

Option	Default	Possible values	Description	Unit
isurf	-1	$x \in \{1, 2, 3, 4, 10\}$	Overrides isurf flag of Namelist PHYSICS if used.	-
lmostlocal	.false.	$x \in \{\text{.false., .true.}\}$	Switch to locally determine Obukhov length	-
lsmoothflux	.false.	$x \in \{\text{.false., .true.}\}$	Switch to create uniform sensible and latent heat flux over domain	-
lneutral	.false.	$x \in \{\text{.false., .true.}\}$	Switch to disable stability corrections	-
z0	-1		Obsolete	
z0mav	-1	$x \in \mathbb{R}, \quad x > 0$	Roughness length of momentum	m
z0hav	-1	$x \in \mathbb{R}, \quad x > 0$	Roughness length of heat	m
thls	-1	$x \in \mathbb{R}, \quad x > 0$	Surface liquid water potential temperature	K
ps	-1	$x \in \mathbb{R}, \quad x > 0$	Surface pressure	Pa
ustin	-1	$x \in \mathbb{R}, \quad x \geq 0$	Prescribed friction velocity	m s^{-1}
wtsurf	-1	$x \in \mathbb{R}$	Prescribed kinematic temperature flux	K m s^{-1}
wqsurf	-1	$x \in \mathbb{R}$	Prescribed kinematic moisture flux	$\text{kg kg}^{-1} \text{m s}^{-1}$
wsvsurf(1:nsv)	0	$x \in \mathbb{R}[100]$	Prescribed surface scalar flux	ppb m s^{-1}
tsoilav	-	$x \in \mathbb{R}[4], \quad x[i] > 0$	Initial soil temperature (for 4 layers, only used if isurf = 1)	K
tsoildeepav	-	$x \in \mathbb{R}, \quad x > 0$	Soil bottom temperature (if isurf = 1)	K
phiwav	-	$x \in \mathbb{R}[4], \quad 0 \leq x[i] \leq 0.472$	Soil moisture (if isurf = 1 and preferably below 0.323)	$\text{m}^3 \text{m}^{-3}$
rootfav	-	$x \in \mathbb{R}[4], \quad 0 \leq x[i] \leq 1, \quad \sum_i x[i] = 1$	Root fraction (if isurf = 1)	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
Cskinav	-1	$x \in \mathbb{R}, x \geq 0$	Heat capacity skin layer (if isurf = 1)	$\text{J K}^{-1} \text{m}^{-2}$
lambdaskinav	-1	$x \in \mathbb{R}, x \geq 0$	Heat conductivity skin layer (if isurf = 1)	$\text{J s}^{-1} \text{K}^{-1} \text{m}^{-2}$
albedoav	-1	$x \in \mathbb{R}, 0 \leq x \leq 1$	Albedo (if isurf = 1)	-
Qnetav	-1	$x \in \mathbb{R}$	Net radiation (if irradiation $\neq 1$ and isurf = 1)	$\text{J s}^{-1} \text{m}^{-2}$
cvegav	-1	$x \in \mathbb{R}, x \geq 0$	Vegetation cover	-
Wlav	-1	$x \in \mathbb{R}, x \geq 0$	Initial water cover on vegetation	m
rsminav	-1	$x \in \mathbb{R}, x \geq 0$	Minimal vegetation resistance (if isurf = 1)	s m^{-1}
rssoilminav	-1	$x \in \mathbb{R}, x \geq 0$	Minimum soil evaporation resistance	-
LAIav	-1	$x \in \mathbb{R}, x \geq 0$	Leaf area index (if isurf = 1)	$\text{m}^2 \text{m}^{-2}$
gDav	-	$x \in \mathbb{R}, x \geq 0$	Correction for evaporation of tall vegetation (if isurf = 1)	-
rsisurf2	0	$x \in \mathbb{R}, x \geq 0$	Vegetation resistance (if isurf = 2)	s m^{-1}
lhetero	.false.	$x \in \{\text{.false., .true.}\}$	Switch to apply heterogeneous surfaces	-
xpatches	2	$x \in \mathbb{N}, 1 \leq x \leq 16$	Amount of patches in the x-direction	-
ypatches	1	$x \in \mathbb{N}, 1 \leq x \leq 16$	Amount of patches in the y-direction	-
land_use(1:16,1:16)	0	$x \in \mathbb{N}, 1 \leq x \leq 10$	Indicator for the land type	-
lolddtable	.false.	$x \in \{\text{.false., .true.}\}$	Switch to use surface.inp.xxx instead of updated surface.<name>.inp.xxx	-
lrsags	.false.	$x \in \{\text{.false., .true.}\}$	Switch to use A-g _s for resistance calculations (if isurf = 1)	-
lCO2Ags	.false.	$x \in \{\text{.false., .true.}\}$	Switch to calculate CO ₂ fluxes with A-g _s (if lrsAgs = .true.)	-
planttype	3	$x \in \{3, 4\}$	Switch between (C)3 and (C)4 plants for A-g _s	-
lrelaxgc	.false.	$x \in \{\text{.false., .true.}\}$	Switch to nudge towards calculated conductivity instead of instantaneous adaptation	-
kgc	0.00113	$x \in \mathbb{R}, 0 < x \leq \text{dtmax}^{-1}$	Response rate for stomatal conductivity	s^{-1}
lrelaxci	.false.	$x \in \{\text{.false., .true.}\}$	Switch to nudge towards calculated internal CO ₂ concentration instead of instantaneous adaptation	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
kci	0.00113	$x \in \mathbb{R}, 0 < x \leq dtmax^{-1}$	Response rate for internal CO ₂ concentration	s ⁻¹
phi	0.472	$x \in \mathbb{R}, x > 0$	volumetric soil porosity	-
phifc	0.323	$x \in \mathbb{R}, x > 0$	volumetric moisture at field capacity	-
phiwp	0.171	$x \in \mathbb{R}, x > 0$	volumetric moisture at wilting point	-
R10	0.23	$x \in \mathbb{R}, x > 0$	Respiration at 10 °C	mg m ⁻² s ⁻¹

2.2.29 Namelist NAMTILT

Option	Default	Possible values	Description	Unit
ltilted	.false.	$x \in \{\text{.false., .true.}\}$	Switch for a tilted boundary layer	-
alfa	0	$x \in \mathbb{R}, -\frac{\pi}{2} \leq x \leq \frac{\pi}{2}$	Tilt angle	rad
lstat	.true.	$x \in \{\text{.false., .true.}\}$	Switch for statistics	-
dtav	dtav_glob	$x = n \cdot dtmax, n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
timeav	timeav_glob	$x = n \cdot dtav, n \in \mathbb{N}^*$	Time interval for writing statistics	s

2.2.30 Namelist NAMTIMESTAT

Option	Default	Possible values	Description	Unit
ltimestat	.false.	$x \in \{\text{.false., .true.}\}$	Switch for calculation of time series	-
dtav	dtav_glob	$x = n \cdot dtmax, n \in \mathbb{N}^*$	Time interval for sampling of statistics	s
iblh_var	-1	$x \in \{-1, -2, -3\}$	Flag for the variable used to calculate boundary-layer height: -1 = virtual pot. temp. θ_v -2 = liquid water pot. temp. θ_l -3 = total humidity q_t	-

Continued on next page

Continued from previous page

Option	Default	Possible values	Description	Unit
iblh_meth	2	$x \in \{1, 2, 3\}$	Flag for the method used to calculate boundary-layer height: 1 = use flux of selected variable 2 = use gradient of selected variable 3 = use a threshold (auto or user specified)	-
blh_thres	-1	$x \in \mathbb{R}, \quad x \geq 0$	Threshold for the selected variable, used only for iblh_thres method	K or kg kg^{-1}
blh_nsamp	4	$x \in \mathbb{N}^*, \quad x \leq \text{kmax}$	Number of levels to integrate over	-

Bibliography

- T. Heus, C. van Heerwaarden, and J. van der Dussen. *Dutch Atmospheric Large Eddy Simulation: user manual*, November 2009.
- M. Khairoutdinov and Y. Kogan. A new cloud physics parametrization in a large-eddy simulation model of marine stratocumulus. *Monthly Weather Review*, 128:229–243, 2000.
- A. Seifert and K.D. Beheng. A double-moment parameterization for simulating autoconversion, accretion and selfcollection. *Atmospheric Research*, 59-60:265–281, 2001.
- A. Seifert and K.D. Beheng. A two-moment cloud microphysics parameterization for mixed-phase clouds. part 1:model description. *Meteorology and Atmospheric Physics*, 92:45–66, 2006.